

# TS-1021: Error 59 - Hard Disk Full

Comm One LLC - Technical Support Documentation

[Support Documentation Index](#)

Friday, March 19, 2010

2:10 AM

*The information in this article applies to:*

All Comm One Software

## ANSWER

Error 59 is an error that is returned when the hard disk fills up. If you are low on disk space, this error most commonly happens during call processing, or during the running of end of month reports. To fix the error, you need to free up disk space on your drive by deleting any unused or old records. You may also want to look at downloading our oldlogs.exe utility so that your call accounting system can automatically purge old call logs.

When you run out of disk space on a drive during call processing, you can corrupt data files or file indexes because there is no disk space to write to and close files. When this happens you can corrupt your data files. Therefore, it is not a good idea to run out of disk space any more often than necessary.

## See Also:

<a href="#">TS-1001: Error: No Records Found</a>
<a href="#">TS-1021: Error 59 - Hard Disk Full</a>
<a href="#">TS-1029: ERROR: Cannot locate the desired version of Foxpro?</a>
<a href="#">TS-1049: What does the error "Exceeded the number of licensed stations" mean?</a>
<a href="#">TS-1050: What does error 1705 mean?</a>
<a href="#">TS-1058: Error loading Call Accounting, Needs Administrator rights.</a>
<a href="#">TS-1064: What is Error 1644 and how do I resolve it?</a>
<a href="#">TS-1084: What is Error 114 and how do I correct it?</a>
<a href="#">TS-1116 - Error 158 when running Advanced IP Capture Utility</a>
<a href="#">TS-1127 - What does the error "Variable NUMLOGS not found" mean?</a>
<a href="#">TS-1136 - A few call records are showing as Unknown Calling Patterns. What does this mean and how do I correct it?</a>
<a href="#">TS-1147: Date is blank in the timr_calls.dbf file for Proximiti</a>

### Comm One LLC

12723 Whisper Creek Cove  
Draper, UT 84020  
801-523-9797  
support@commone.com  
Last Reviewed: 03/17/2010  
TS-1021

TS-1021	Date: 06/11/2003 Keywords: Error 59
---------	--